### **LAMMPS Installation Instructions**

# **Step 1:** Download the lammps installer from website.

#### https://packages.lammps.org/windows.html




- Either, a regular multi-threaded LAMMPS executable called 1mp. This should always work.

  Or: a multi-threaded LAMMPS executable that also supports parallel execution via MPI message passing. This executable is called 1mp and requires installation of a suitable MPICH2 package to work. the LAMMPS manual in PDF format.


  the colvans reference manual in PDF format guides for specific packages or styles several additional PDF format guides for specific packages or styles. The potential files bundled with the LAMMPS source code most of the example inputs, reference outputs and related files the benchmark inputs and reference outputs.

  the tools binary2txt, chain, msi2lmp, abf\_integrate, createatoms, ocl\_get\_devices, lammps-shell


# Step 2: Run the installer




Step 3: Copy or remember the path where LAMMPS will be installed




Step 4: Press Windows start Button and type environment




Step 5 : Open the Edit the System Environment Variables tab and click on Environment Variables



Step 6: Find the path variable in System Variables and click edit



#### Step 7 Click on New and Copy the path there and click Ok



# Step 8: Go to desktop, Press shift and right-click and open a Powershell Terminal. Type lmp serial.exe –help

If the installation was correct, you should see something like this:

```
+ FullyQualifiedErrorId : UnauthorizedAccess
PS D:\Work\MD-Short-Term-Course> lmp_serial.exe -help
Large-scale Atomic/Molecular Massively Parallel Simulator - 24 Jan 2020
Usage example: C:\Program Files\LAMMPS 64-bit 24Jan2020\bin\lmp_serial.exe
-var t 300 -echo screen -in in.alloy
List of command line options supported by this LAMMPS executable:
echo none/screen/log/both : echoing of input script (-e)
                           : print this help message (-h)
-help
-in filename
                           : read input from file, not stdin_(-i)
-kokkos on/off ...
                           : turn KOKKOS mode on or off (-k)
-log none/filename
                            : where to send log output (-l)
                           : which exe in a multi-exe mpirun cmd (-m)
mpicolor color
                           : disable writing log.cite file (-nc)
-nocite
package style ...
                           : invoke package command (-pk)
partition size1 size2 ... : assign partition sizes (-p)
plog basename
                          : basename for partition logs (-pl)
pscreen basename
                          : basename for partition screens (-ps)
-restart2data rfile dfile ...: convert restart to data file (-r2data)
-restart2dump rfile dgroup dstyle dfile ...
```